

Typesetting dropped capitals with LaTeX

Daniel Flipo

daniel.flipo@free.fr

1 Introduction

The file `lettrine.sty`¹, provides a command `\lettrine` which requires two mandatory arguments, and an optional one.

Adding `\usepackage{lettrine}` in the preamble of a document defines the command `\lettrine`, the simplest use of which is `\lettrine{<letter>}{<text>}`. It produces a dropped capital `<letter>` (2 lines high), followed by `<text>` typeset in small caps, and the rest of the paragraph is wrapped around the dropped capital.

The `\lettrine[<options>]{<letter>}{<text>}` command accepts various optional arguments to control the size and layout of the dropped capital and match the requirements described in the books

- + “Lexique des règles typographiques en usage à l’Imprimerie nationale” troisième édition (1994), ISBN-2-11-081075-0,
- + “Mise en page et impression” Yves Perrousseau, ISBN-2-911220-01-3.

The parameters can be set using the `key=value` syntax:

- + `lines=<integer>` sets how many lines the dropped capital will occupy (default=2);
- + `depth=<integer>` sets the number of lines to be reserved under the baseline, this is meant for dropped capital with positive depth, like Q (default=0);
- + `lhange=<decimal>` ($0 \leq \text{lhange} \leq 1$) sets how much of the dropped capital’s width should hang into the margin (default=0);
- + `loversize=<decimal>` ($-1 < \text{loversize} \leq 1$) enlarges the dropped capital’s height: with `loversize=0.1` its height is enlarged by 10% so that it raises above the top paragraph’s line (default=0);
- + `lraise=<decimal>` does not affect the dropped capital’s height, but moves it up (if positive), down (if negative); useful with capitals like J or Q which have a positive depth, (default=0);
- + `findent=<dimen>` (positive or negative) controls the horizontal gap between the dropped capital and the indented block of text (default=0pt);
- + `nindent=<dimen>` shifts all indented lines, starting from the second one, horizontally by `<dimen>` (this shift is relative to the first line, default=0.5em);
- + `slope=<dimen>` can be used with dropped capitals like A or V to add `<dimen>` (positive or negative) to the indentation of each line starting from the third one (no effect if `lines=2`, default=0pt);

¹The file described in this section has version number v2.83 and was last revised on 2025-12-06.

- + `ante=<string>` can be used to typeset *<string>* before the dropped capital (typical use is for French guillemets starting the paragraph).
- + `image[=true]` will force `\lettrine` to replace the letter normally used as dropped capital by an image in eps format (latex) or in pdf, jpg, png, etc. format (pdflatex, xelatex, lualatex); this requires the `graphicx` package to be loaded in the preamble. For instance `\lettrine[image=true]{A}{n exemple}` or just `\lettrine[image]{A}{n exemple}` will load `A.eps`, `A.jpg`, `A.png` or `A.pdf` instead of letter A. The string `A` will be used as “actualtext” for PDF tagging purposes. If your image is meant to be read as “A” but is loaded under another name, you should add `actualtext=A` as an option to `\lettrine`.
- + `viewport=<llx lly urx ury>` is passed to `\includegraphics` (same four dimen parameters); when present, `\lettrine` only considers the contents of the rectangle defined by its lower left and upper right corners to compute the scaling ratio (which will apply to the whole image). It’s up to the user to ensure that the rest of the image will not overwrite the surrounding text, f.i. providing a `\vspace*{...}` in case a significant part sticks out on top of the defined rectangle. This option may be useful in case the letter covers only a limited part of the image, see <https://tex.stackexchange.com/questions/693270/> for an example, or when the image’s bounding box is inaccurate.
- + `grid[=true]` will force the vertical skip added above the paragraph starting with `\lettrine` to be rounded up to an integer number of `\baselineskip`. This option is meant for grid typesetting.
- + `nextpage[=true]`; if a paragraph starting with a dropped cap begins too low on a page to fit in, a warning is issued; this flag controls whether the whole paragraph should be moved to the top of next page or not. This option is not recommended, there are often better fixes for such situations: reducing the dropped cap’s height, shortening some previous paragraph, enlarging the page...
- + `novskip=<dimen>` overrides `\DiscardVskip` (default=1pt). In some cases (see options `lraise`, `loversize` or accentuated dropped capitals,...) the top of the dropped capital will raise above the top of following text (usually in small caps), this will trigger a corresponding vertical skip above the paragraph starting with `\lettrine`, *only if* this skip exceeds `\DiscardVskip`. Consider enlarging `novskip` (or `\DiscardVskip`) to prevent small vertical skips from being rounded up to `\baselineskip` when using the ‘grid’ option.
- + `realheight[=true]` will compute the default height of the initial so that the top of it is exactly aligned with the top of the text entered as second mandatory argument of `\lettrine` taking possible accents into account. Otherwise, the default height is computed using a customisable string `\LettrineSecondString` instead of the real argument. For backward compatibility, option `realheight` defaults to `false` and `\LettrineSecondString` to ‘x’.

You probably don’t need this option if you choose to typeset the second mandatory argument of `\lettrine` in small caps (the default). If you change `\LettrineTextFont` to `\relax` or `\upshape`, consider these two examples:

`\lettrine{H}{ello}` you might like the top of the ‘H’ to be aligned with the top of the ‘ll’ rather than with the top of the ‘e’, adding option `realheight` does the trick: `\lettrine[realheight]{H}{ello}`.

Global variants : `\LettrineRealHeighttrue` or (without the `realheight` option) `\renewcommand{\LettrineSecondString}{1}`.

`\lettrine{L}{a misère}` option `realheight=true` would align with the top of the 'L' with the top of the grave accent, the default is probably better (top of the 'L' aligned with the top of the non accented letters).

- + `refstring` with no value, is meant for fancy initials with irregular heights (i.e. taken in fonts like Yinit (OpenType), `cfr-initials`,...). Option `refstring` forces the `\fontsize` computations to be run on the initial given as `\lettrine`'s first mandatory argument instead of the reference string `\LettrineTestString`. In most cases, this option should *not* be used: think of accentuated initials or capitals with optical correction.

`refstring=<string>` can be used to override `\LettrineTestString`, the default reference string (option *seldom useful*).

Example: `\lettrine[lines=4, lraise=0.1, nindent=0em, slope=-.5em]{V}{oici} un exemple ...`

Coloured initials are available in conjunction with package `color`, examples:

`\lettrine{\textcolor{red}{A}}{n} example` or

`\lettrine{\textcolor[gray]{0.5}{A}}{nother} one`

see package `color` for the syntax of colour commands. Another possibility to colour initials globally is described below, see `\LettrineFontHook`.

Three dimensions, `\LettrineHeight`, `\LettrineDepth` and `\LettrineWidth` hold the final size of the initial (*height* and *depth* being measured from the paragraph's *n*-th baseline if `lines=n`).

Have a look at files `lettrine-demo-fr.tex` and `lettrine-demo-lua.tex` and at the resulting PDFs in the `doc` folder to see the possible usage of these parameters.

Starting with version 2.30, the default settings can easily be specified as options passed to the `lettrine` package. These options are the same as those of the `\lettrine` command previously described²: f.i. `\usepackage[lines=3]{lettrine}` will set the default to three lines of text. Options passed to the `lettrine` package override the defaults set in the `lettrine.cfg` file (see below) and will be overridden by options passed to the `\lettrine` command.

The default settings can also be customized in a config file `lettrine.cfg` (backward compatibility). The following list shows the syntax to set them and their default values:

- + `\setcounter{DefaultLines}{2}`,
- + `\setcounter{DefaultDepth}{0}`,
- + `\renewcommand{\DefaultLoversize}{0}`,
- + `\renewcommand{\DefaultLraise}{0}`,
- + `\renewcommand{\DefaultLhang}{0}`,
- + `\setlength{\DefaultFindent}{0pt}`,
- + `\setlength{\DefaultNindent}{0.5em}`,

²With the exception of `ante` and `viewport` which do not make sense for a global usage.

- + `\setlength{\DefaultSlope}{0pt}`.
- + `\setlength{\DiscardVskip}{1pt}`,
- + `\LettrineImagefalse`,
- + `\LettrineOnGridfalse`,
- + `\LettrineMoveAtEOPfalse`,
- + `\LettrineRealHeightfalse`.

Instead of giving optional parameters to the `\lettrine` command, it is possible to set them on a per character basis in a second config file (suggested by Pascal Kockaert): `\renewcommand{\DefaultOptionsFile}{<filename>}` in the preamble will force this file to be read 'AtBeginDocument'. Alternatively, `\usepackage[optionsfile=<filename>]{lettrine}` produces the same effect. See examples of such config files in the subdirectory `contrib`.

The idea is to provide settings for specific fonts, or to define suitable parameters for some initials like A or V, for instance

```
\LettrineOptionsFor{A}{slope=0.5em, findent=-1.5em, nindent=.7em}
```

Options passed this way are meant to fine tune how the text will be wrapped around the initial; for convenience *inside* `\LettrineOptionsFor` *only*, `\LettrineWidth` can be used instead of `em` as a unit length.

Since version 2.70, these commands are also allowed in the document's preamble. Mixing `\LettrineOptionsFor` commands in the preamble and in an external config file is not recommended: remember that if an options file is declared, the settings it holds will be taken into account 'AtBeginDocument' thus possibly overriding `\LettrineOptionsFor` commands in the preamble.

Anyway, the settings read from this file will be overridden by the optional arguments eventually given to the `\lettrine` command.

More customisation possibilities are offered by the next four commands:

- + `\renewcommand{\LettrineFontHook}{}`,
- + `\renewcommand{\LettrineTextFont}{\scshape}`,
- + `\renewcommand{\LettrineTestString}{EFTZ}`,
- + `\renewcommand{\LettrineSecondString}{x}`,

`\LettrineTextFont` sets the font used for the second argument of `\lettrine`, its default definition is `\newcommand{\LettrineTextFont}{\scshape}` (second argument in small caps), this can be changed using `\renewcommand`.

`\LettrineTestString` and `\LettrineSecondString` provide reasonable defaults for Latin scripts (EFTZ and x). For other scripts they *should be changed* respectively to uppercase and lowercase letters of the given script, as the dropped cap's height computation is based on these strings; another possibility is to use the previously described `refstring` and `realheight` options.

`\LettrineFont` *is not customisable* see `\LettrineFontHook` below, it sets the font used for the dropped capital, usually the current font in a (large) size, computed

automatically from the number of lines it will fill: the font size is computed so that, a *standard* dropped capital (say Z, not Å) when sitting on its baseline, gets its top aligned with the top of the following text (provided `loversize = 0` and `lines ≥ 2`). When `lines=1`, size is computed as if `lines` was 2.

A hook `\LettrineFontHook` is provided to change the font used for the dropped capital, syntax follows LaTeX's low-level font interface (see LaTeX Companion III, section I-9.3), the `\selectfont` command is issued by `\LettrineFont`:

```
\renewcommand{\LettrineFontHook}{\fontfamily{ppl}\fontseries{bx}%  
                                \fontshape{sl}}
```

selects Palatino bold expanded slanted for the dropped capital.

With LuaLaTeX or XeLaTeX changing the lettrine's font is even easier, simply use the `\fontspec` command:

```
\renewcommand{\LettrineFontHook}{\fontspec{LinLibertine_I.otf}}
```

will switch to Linux Libertine Initials.

`\LettrineFontHook` can also be used to change the colour of all initials in a (part of) document: `\renewcommand{\LettrineFontHook}{\color[gray]{0.5}}`

will colour the initials following this command in grey. A `\color` command can be added in `\LettrineTextHook` if the text following the dropped cap requires the same or another colour.

Important notice: the sizing works fine with *fully scalable* fonts (like the standard PostScript or OpenType fonts), but might not work well with CM/EC fonts which have two limitations: only a limited number of sizes is available by default (precise adjustments are impossible), and the largest size (25pt or 35pt) is often too small. The CM fonts are available in PostScript type1 format for free (courtesy of BlueSky/Y&Y), to make them fully scalable, it is mandatory to add `\usepackage{type1cm}` in the preamble of your document. The EC fonts are also available in type1 format for free (thanks to Vladimir Volovich, they are called cm-super), and adding `\usepackage{type1ec}`³ in the preamble will make them fully scalable too. So, if you want `lettrine.sty` to work properly with CM or EC fonts, you will need *PostScript versions* of these fonts *and* one of the packages `type1cm.sty` or `type1ec.sty`.

The LM fonts are a good replacement for both CM and EC fonts they are fully scalable, so you should use them instead of CM or EC fonts. `\usepackage{lmodern}` is the command to switch them on (add `\usepackage[T1]{fontenc}` when composing in one of the western languages other than English in order to get proper hyphenation).

You can also consider using one of the standard PostScript fonts (Palatino, Times, Utopia...), or any OpenType font, they are fully scalable too!

Breaking change in version 2.50: in order to improve the alignment of side by side parboxes starting with a dropped cap, the internals of the `\lettrine{}` command have changed. Formerly, the initial was completely smashed (`height=0`, `depth=0`) and a `\vskip` was added in case the initial stuck out too much above the paragraph's first baseline. From version 2.50 on, the initial gets a null `depth` and its proper `height` (measured from the paragraph's first baseline, please note that it is different from `\LettrineHeight`). This change has the following side effect: in multicolumn typesetting, when a dropped cap starts a column and sticks out significantly above the baseline, it might be necessary to 'smash' the dropped cap and eventually to add a

³This package, available on CTAN, was first released on 2002/07/30.

`\vspace{}` before the multicolumn environment. See `lettrine-demo-fr.pdf` p. 4 for an example. Using the rollback mechanism to switch back to version 2.40 is another option: `\usepackage{lettrine}[=v2.4]`.

New in version 2.60: the `\lettrine` command is now compatible with right to left typesetting, with LuaLaTeX and XeLaTeX (+babel or polyglossia). With XeLaTeX, file `lettrine-xetex-bidi.def` (v0.8 [2022/11/06]) is automatically loaded by the bidi package; it redefines the `\@lettrine` command based on version 2.30 of lettrine. This code is *incompatible* with versions 2.50 and newer, you can safely remove `lettrine-xetex-bidi.def` when installing v2.60 or newer of lettrine.

Known issues:

- + Starting with version 2.80, the lettrine package issues a warning in case a paragraph starting with a dropped capital occurs at the end of some page thus requiring manual page-breaking; it's up to the user to figure out how to best fix the issue (enlarging the page, shortening some previous paragraph...). A new option `nextpage` has also been added, when set to `true`, the whole paragraph is moved to the top of next page... leaving a blank at the end of the previous page.
- + `\lettrine` works within 'quote' 'quotation', 'abstract' environments but does not work within 'verse' environments. It doesn't work either in 'center' environments except with option `[lines=1]`.
- + `\lettrine` does not work within lists.
- + If `\lettrine` is used inside any environment, it is *mandatory* to end the paragraph starting with the dropped capital *inside* the environment; adding a `\par` command before the end of environment usually fixes placement issues.
- + The LaTeX `\raggedright` command doesn't work well with the TeX `\parshape` command used internally by `\lettrine`. Please use the `\RaggedRight` command from the `ragged2e` package together with appropriate settings, f.i. `\setlength{\RaggedRightRightskip}{0pt plus .1\hsize}`. See <https://tex.stackexchange.com/questions/97808/> for details.
- + If a *list* has to be included in a paragraph starting with `\lettrine`, it is necessary to add the command `\parshape=0` just after the end of the list (starting a new paragraph just before or just after the list works too). Remember that 'quote', 'quotation', 'abstract' environments are implemented as *lists* in LaTeX.
- + If you are facing some slight height inaccuracy for a dropped capital, you can try option `refstring`; this option is meant for fancy (unaccented) initials. Informations about targeted and effective initial's height are available in the `.log` file. Using LuaTeX or XeTeX engines with OpenType fonts may be an option (some TFM files for Type1 fonts are slightly inaccurate).
- + `\LettrineTestString`'s value has changed over the time; these changes may result in slight size differences for the initial. Starting with version 2.2, the lettrine package takes advantage of the rollback facilities recently introduced by the LaTeX Team⁴. Three rollback versions are provided in order to produce exactly the same output as with former versions: you can request

⁴A LaTeX kernel dated 2018-04-01 or newer is required.

`\usepackage{lettrine}[=v1.6]`⁵ for 1999-2012 documents or
`\usepackage{lettrine}[=v1.9]` (documents from 2012 to July 2018) or
`\usepackage{lettrine}[=v2.0]` (August 2018). Using any date in ISO format
works too: `\usepackage{lettrine}[=2014-03-15]` will load v1.9.

⁵Don't forget the = sign!

2 TeXnical details

The lettrine package uses the rollback mechanism introduced by the LaTeX Team to provide easier backward compatibility. The current release requires a LaTeX version not older than 2022-06-01 (kernel packages `ltxkeys` and `xfp` are required).

```
1 \DeclareRelease{v1.6}{1999-03-03}{lettrine-2006-03-17.sty}
2 \DeclareRelease{v1.9}{2012-07-20}{lettrine-2015-08-31.sty}
3 \DeclareRelease{v2.0}{2018-07-21}{lettrine-2018-08-18.sty}
4 \DeclareRelease{v2.3}{2022-09-25}{lettrine-2022-09-25.sty}
5 \DeclareRelease{v2.4}{2023-04-18}{lettrine-2023-04-18.sty}
6 \DeclareCurrentRelease{}{2025-11-25}
```

Default initializations: define the necessary counters, lengths, and commands to hold the default settings and set these default settings. They can be overwritten in file `lettrine.cfg`.

```
7 \newcounter{DefaultLines}
8 \setcounter{DefaultLines}{2}
9 \newcounter{DefaultDepth}
10 \newcommand{\DefaultOptionsFile}{}
11 \newcommand{\DefaultLoversize}{0}
12 \newcommand{\DefaultLraise}{0}
13 \newcommand{\DefaultLhang}{0}
14 \newdimen\DefaultFindent
15 \setlength{\DefaultFindent}{\z@}
16 \newdimen\DefaultNindent
17 \setlength{\DefaultNindent}{0.5em}
18 \newdimen\DefaultSlope
19 \setlength{\DefaultSlope}{\z@}
20 \newdimen\DiscardVskip
21 \setlength{\DiscardVskip}{1pt}
22 \newif\ifLettrineImage
23 \newif\ifLettrineOnGrid
24 \newif\ifLettrineRealHeight
25 \newif\ifLettrineMoveAtEOP
```

Then let's define the necessary internal counters, lengths, and commands.

```
26 \newsavebox{\L@lbox}
27 \newcounter{L@lines}
28 \newcounter{L@depth}
29 \newdimen\L@Pindent
30 \newdimen\L@Findent
31 \newdimen\L@Nindent
32 \newdimen\L@lraise
33 \newdimen\L@first
34 \newdimen\L@next
35 \newdimen\L@slope
36 \newdimen\L@height
37 \newdimen\L@novskip
38 \newdimen\L@target@ht
39 \newdimen\L@target@dp
40 \newdimen\L@target@tht
```



```

41 \newdimen\LettrineWidth
42 \newdimen\LettrineHeight
43 \newdimen\LettrineDepth
44 \newdimen\L@finalht
45 \newdimen\L@finaldp
46 \newcommand*\L@file{}
47 \newcommand*\L@hang{}
48 \newcommand*\L@oversize{}
49 \newcommand*\L@raise{}
50 \newcommand*\L@ante{}
51 \newcommand*\L@actual{}
52 \newif\ifL@image
53 \newif\ifL@grid
54 \newif\ifL@nextpage
55 \newif\ifL@realh
56 \let\ifL@RTL\iffalse
57 \newcommand*\L@viewport{}

```

`\LettrineTestString` As some font designers apply optical correction to capitals C, G, O, or Q (they are slightly taller than ‘T’ or ‘Z’), they are better left out of `\LettrineTestString`. EFTZ should be a good default for most fonts.

```
58 \newcommand*\LettrineTestString}{EFTZ}
```

Load a local config file if present in LaTeX’s search path.

```

59 \InputIfFileExists{lettrine.cfg}
60   {\typeout{Loading lettrine.cfg}}
61   {\typeout{lettrine.cfg not found, using default values}}

```

Global package options enable to override the default values given above to generic parameters. These may be overridden again by options passed to the `\lettrine[]{}{}` command. This code is based on `ltkeys.dtx`.

```

62 \DeclareKeys[LettrineGlobal]
63   {
64     lines.code      = \setcounter{DefaultLines}{#1} ,
65     depth.code     = \setcounter{DefaultDepth}{#1} ,
66     lhang.store    = \DefaultLhang ,
67     loversize.store = \DefaultLoversize ,
68     lraise.store   = \DefaultLraise ,
69     findent.code   = \setlength{\DefaultFindent}{#1} ,
70     nindent.code   = \setlength{\DefaultNindent}{#1} ,
71     slope.code     = \setlength{\DefaultSlope}{#1} ,
72     novskip.code   = \setlength{\DiscardVskip}{#1} ,
73     image.if       = LettrineImage ,
74     grid.if        = LettrineOnGrid ,
75     nextpage.if    = LettrineMoveAtEOP ,
76     realheight.if  = LettrineRealHeight ,
77     actualtext.store = \L@actual ,
78     refstring.default:n = \L@initial ,
79     refstring.store = \LettrineTestString ,
80     optionsfile.store = \DefaultOptionsFile
81   }
82 \ProcessKeyOptions[LettrineGlobal]

```

Ditto for the `\lettrine` command's options.

```
83 \DeclareKeys[LettrineLocal]
84 {
85   lines.code      = \setcounter{L@lines}{#1}      ,
86   depth.code     = \setcounter{L@depth}{#1}      ,
87   lhang.store    = \L@hang                        ,
88   loversize.store = \L@oversize                  ,
89   lraise.store   = \L@raise                       ,
90   ante.store     = \L@ante                        ,
91   findent.code   = \setlength{L@Findent}{#1}     ,
92   nindent.code   = \setlength{L@Nindent}{#1}     ,
93   slope.code     = \setlength{L@slope}{#1}       ,
94   novskip.code   = \setlength{L@novskip}{#1}     ,
95   image.if       = L@image                        ,
96   viewport.store = \L@viewport                    ,
97   grid.if        = L@grid                         ,
98   nextpage.if    = L@nextpage                     ,
99   realheight.if  = L@realh                       ,
100  actualtext.store = \L@actual                     ,
101  refstring.default:n = \L@initial                 ,
102  refstring.store  = \L@refstring                   ,
103 }
```

Read the per letter options file 'AtBeginDocument'.

```
104 \AtBeginDocument{%
105   \ifx\DefaultOptionsFile\@empty
106   \else
107     \InputIfFileExists{\DefaultOptionsFile}%
108     {\PackageWarning{lettrine.sty}%
109      {File \DefaultOptionsFile\space loaded!}%
110     }%
111     {\PackageWarning{lettrine.sty}%
112      {File \DefaultOptionsFile\space not found!}%
113     }%
114   \fi}
```

`\LettrineOptionsFor` This command sets the values of parameters on a per character basis, for instance:
`\LettrineOptionsFor{A}{slope=0.6em, findent=-1em, nindent=0.6em}`

```
115 \newtoks\Lettrine@tweaks
116 \newcommand*{\LettrineOptionsFor}[2]{%
117   \Lettrine@tweaks=\expandafter{\the\Lettrine@tweaks
118     \@lettrine@optionsfor{#1}{#2,}}
```

The internal `\@lettrine@optionsfor` checks if its first argument matches the current initial, if so it passes the options (second argument) to `\SetKeys`.

```
119 \newcommand*{\@lettrine@optionsfor}[2]{%
120   \edef\L@tmpa{#1}%
```

Gobble potential color commands for the initial.

```
121   \begingroup
```

```

122 \def\color##1##{\L@color{##1}}%
123 \let\L@color\@gobbletwo
124 \def\textcolor##1##{\L@textcolor{##1}}%
125 \def\L@textcolor##1##2##3{##3}%
126 \xdef\L@tmpb{\L@initial}%
127 \endgroup
128 \ifx\L@tmpa\L@tmpb \SetKeys[LettrineLocal]{#2}\fi
129 }

```

`\LettrineTextFont` In French, small caps usually follow the initial.

```

130 \newcommand*{\LettrineTextFont}{\scshape}
131 \newcommand*{\LettrineSecondString}{x}

```

`\LettrineFontHook` `\LettrineFontHook` enables to select another font for the dropped capital. Its default definition is empty (the current text font is used).

```

132 \newcommand*{\LettrineFontHook}{}

```

`\computeL@height` The default size for the dropped capital is computed so that the top of it is exactly aligned with the top of the following text; an extra height (positive or negative) may be added globally by redefining `\Defaultloversize` or locally using optional argument `loversize=`. If `lines=1`, the default size for the dropped capital is computed as if `lines=2`.




Figure 1: Initial's targeted dimensions (`\lines = 4`, `\raise = 0`)

`\computeL@height` computes the targeted height for the dropped capital and stores it into `\L@target@tht`. This height only depends on `L@lines` and `\L@target@ht` (the height of the following text, see fig. 1). So options *must* be read and `\L@target@ht` be properly initialised *before* executing `\computeL@height` (see below in `\lettrine` code). `\L@height` is set to `\L@target@tht` raised by the `\L@oversize` factor.

```

133 \def\computeL@height{%

```

As `\baselineskip` might be a rubber length, let's convert it into a 'dimen' using `\@tempdima`.

```

134 \@tempdima=\baselineskip
135 \setlength{\L@target@dp}{\value{L@lines}\@tempdima}%
136 \ifnum\value{L@lines}>1

```

```

137 \addtolength{\L@target@dp}{-\@tempdima}%
138 \else
139 \addtolength{\L@target@ht}{\L@target@dp}%
140 \setlength{\L@target@dp}{\z@}%
141 \fi
142 \setlength{\L@target@tth}{\L@target@ht}%
143 \addtolength{\L@target@tth}{\L@target@dp}%
144 \setlength{\L@height}{\L@target@tth}%
145 \addtolength{\L@height}{\L@oversize\L@target@tth}%
146 }

```

`\compute@fontsize` After executing `\computeL@height`, `\L@height` holds the exact height required for the dropped capital, nothing more is needed if the initial is a picture, otherwise we need to compute the matching `\fontsize`'s value. This is done by measuring the height of a “reference” capital (i.e. either listed in `\LettrineTestString` or the initial itself). This command compares the height of a “reference” capital scaled by `\fontsize` with argument `\L@height`, to `\L@height` (the required height for the initial) to compute a ratio `\L@factor` (decimal number). Then, the initial will be scaled by `\L@factor\L@height`. Starting with v2.40, `\L@factor` is computed by `\fpeval` which is now part of LaTeX kernel.

If the option `refstring` is set in the `\lettrine` command the initial itself is taken as reference to compute `\fontsize`, this can be handy when working with fancy fonts (i.e. cfr-initials, Yinit). In most cases, the default is a better choice.

```

147 \def\compute@fontsize{%
148 \ifx\L@refstring\@empty
149 \def\Lettrine@RefString{\LettrineTestString}%
150 \else
151 \def\Lettrine@RefString{\L@refstring}%
152 \fi
153 \settoheight{\@tempdima}{\LettrineFontHook
154 \fontsize{\L@height}{\L@height}\selectfont
155 \Lettrine@RefString}%
156 \ifdim\@tempdima=\z@
157 \PackageWarning{lettrine}{Unable to compute \protect\fontsize!%
158 \MessageBreak \protect\LettrineTestString\space empty? reported}%
159 \def\L@factor{1}%
160 \else
161 \def\L@factor{\fpeval{\the\L@height/\the\@tempdima}}%
162 \fi
163 }

```

`\LettrineFont` `\fontsize`'s argument providing the requested `\L@height` is `\L@factor\L@height`.

```

164 \newcommand*{\LettrineFont}{%
165 \LettrineFontHook
166 \fontsize{\L@factor\L@height}{\L@factor\L@height}%
167 \selectfont
168 }

```

`\setupL@lbox` `\computeL@dimens` The next (internal) command computes the width, height and depth requested for the initial (letter or image) and stores them in `\LettrineWidth`, `\LettrineHeight` and `\LettrineDepth`.

```

169 \def\computeL@dimens{%
170   \computeL@height
171   \ifL@image
172     \ifx\L@viewport\@empty
173       \settoheight{\LettrineWidth}{%
174         \includegraphics[height=\L@height]{\L@initial}}%
175     \else
176       \settoheight{\LettrineWidth}{%
177         \expanded{\noexpand\includegraphics%
178           [viewport=\L@viewport, height=\L@height]{\L@initial}}%
179         }%
180     \fi
181     \setlength{\LettrineHeight}{\L@height}%
182     \setlength{\LettrineDepth}{\z@}%
183 \else
184   \compute@fontsize
185   \settoheight{\LettrineWidth}{\LettrineFont \L@initial}%
186   \settoheight{\LettrineHeight}{\LettrineFont \L@initial}%
187   \settodepth{\LettrineDepth}{\LettrineFont \L@initial}%
188 \fi
189 }

```

The next command actually stores the dropped cap in the `\L@lbox` box, it will be executed (only once) in horizontal mode to prevent tagging issues.

```

190 \def\setupL@lbox{%
191   \ifL@image
192     \ifx\L@actual\@empty \edef\L@actual{\L@initial}\fi
193     \ifx\L@viewport\@empty
194       \sbox{\L@lbox}{\includegraphics%
195         [height=\L@height, actualtext=\L@actual]{\L@initial}}%
196     \else
197       \sbox{\L@lbox}{%
198         \expanded{\noexpand\includegraphics%
199           [viewport=\L@viewport, height=\L@height,
200             actualtext=\L@actual]{\L@initial}}%
201         }%
202     \fi
203 \else
204   \compute@fontsize
205   \sbox{\L@lbox}{\LettrineFont \L@initial}%
206 \fi
207 }
208 }

```

`\lettrine` Now let's define the `\lettrine` command.

```

209 \NewDocumentCommand\lettrine{ O{} m m }{%
210   \def\L@initial{#2}\def\L@refstring{}\def\L@viewport{}}%

```

First reset the parameters to their default values:

```

211   \setcounter{L@lines}{\value{DefaultLines}}%
212   \setcounter{L@depth}{\value{DefaultDepth}}%
213   \renewcommand*{\L@hang}{\DefaultLhang}%
214   \renewcommand*{\L@oversize}{\DefaultLoversize}%

```

```

215 \renewcommand*{\L@raise}{\DefaultLraise}%
216 \renewcommand*{\L@ante}{}%
217 \renewcommand*{\L@actual}{}%
218 \setlength{\L@Findent}{\DefaultFindent}%
219 \setlength{\L@Nindent}{\DefaultNindent}%
220 \setlength{\L@slope}{\DefaultSlope}%
221 \setlength{\L@novskip}{\DiscardVskip}%
222 \ifLettrineImage\L@imagetrue\else\L@imagefalse\fi
223 \ifLettrineOnGrid\L@gridtrue\else\L@gridfalse\fi
224 \ifLettrineMoveAtEOP\L@nextpagetrue\else\L@nextpagefalse\fi
225 \ifLettrineRealHeight\L@realhtrue\else\L@realhfalse\fi

```

Take the local options passed to `\lettrine` into account to compute `\L@target@ht` which depends on option `realheight`, before eventually reading the per character config file.

```

226 \SetKeys[LettrineLocal]{#1}%
227 \settoheight{\L@target@ht}{\LettrineTextFont{\LettrineSecondString}}%
228 \ifL@realh
229   \def\@tempa{#3}%
230   \ifx\@tempa@empty
231     \PackageWarning{lettrine.sty}%
232       {Empty second argument, \MessageBreak
233        ignoring option `realheight';}%
234   \else
235     \settoheight{\L@target@ht}{\LettrineTextFont{#3}}%
236   \fi
237 \fi

```

Take the per character options into account if any. For these options some parameters' values `findent`, `nindent` and `slope` —which do not influence the initial's size— may be given relative to `\LettrineWidth`, which needs to be computed before.

```

238 \edef\@tempa{\the\Lettrine@tweaks}%
239 \ifx\@tempa@empty
240 \else
241   \computeL@dimens
242   \the\Lettrine@tweaks

```

As local options always prevail, read again the optionnal argument of `\lettrine`.

```

243 \SetKeys[LettrineLocal]{#1}%
244 \fi

```

Compute the final values of `\LettrineWidth`, `\LettrineHeight` and `\LettrineDepth`:

```

245 \computeL@dimens

```

Start a new paragraph and compute in `\L@finalht` the height of the top part of the dropped capital which finally raises above the paragraph's first baseline and in `\L@finaldp` the final depth of the dropped capital.

The basis for `\L@raise` (and `\L@oversize`, see `\LettrineFont`) is `\L@target@tth`.

```

246 \par
247 \setlength{\L@finalht}{\LettrineHeight}%
248 \setlength{\L@lraise}{\L@raise\L@target@tth}%

```

```

249 \addtolength{\L@finalht}{\L@lraise}%
250 \ifnum\value{L@lines}>\@ne
251   \@tempcnta=\value{L@lines}%
252   \advance\@tempcnta \m@ne
253   \@tempdima=\@tempcnta\baselineskip
254   \addtolength{\L@finalht}{-\@tempdima}%
255   \setlength{\L@finaldp}{\@tempdima}%
256   \addtolength{\L@finaldp}{-\L@lraise}%
257   \addtolength{\L@finaldp}{\LettrineDepth}%
258   \addtolength{\L@lraise}{-\@tempdima}%
259 \fi

```

Print some informations about accuracy to the log file,

```

260 \begingroup
261 \def\IeC##1{##1}%
262 \@tempdima=\L@oversize pt\relax
263 \PackageInfo{lettrine.sty}%
264 {Targeted height = \the\L@target@ttht\MessageBreak
265 (for loversize=0, accent excluded),\MessageBreak
266 Lettrine height = \the\LettrineHeight\space (#2)%
267 \ifdim\@tempdima>\z@\space loversize=\L@oversize\fi;%
268 \MessageBreak reported}%
269 \endgroup

```

When `\L@finalht` is larger than `\baselineskip - \L@novskip` and the `grid` option is `true`, let's skip an integer number of `\baselineskip` (and smash the dropped cap, see below).

```

270 \@tempdima=\L@finalht
271 \advance\@tempdima \L@novskip
272 \@tempdimb=\baselineskip
273 \ifdim\@tempdima>\@tempdimb
274   \ifL@grid
275     \@tempcnta=\z@
276     \loop\ifdim\@tempdima>\@tempdimb
277       \advance\@tempcnta \@ne
278       \advance\@tempdima -\@tempdimb
279     \repeat
280     \vskip\@tempcnta\baselineskip
281 \fi
282 \fi

```

Compute the remaining vertical space left on the current page using TeX lengths `\pagetotal` and `\pagegoal`; always warn if the remaining space is less than the depth of the dropped cap' depth `\L@finaldp`. Move the whole paragraph to next page if `nextpage=true` (default is false).

```

283 \@tempdima=\pagegoal
284 \advance\@tempdima by -\pagetotal
285 \advance\@tempdima by -\baselineskip
286 \ifdim\@tempdima < \L@finaldp
287   \@tempdimb=\L@finaldp
288   \advance\@tempdimb by -\@tempdima
289   \PackageWarning{lettrine}{%
290     *** ATTENTION REQUIRED ***\MessageBreak

```

```

291     The dropped cap #2 doesn't fit on page \thepage.%
292     \MessageBreak Missing vertical space: \the\@tempdimb.
293     \MessageBreak
294     \ifL@nextpage The whole paragraph will be moved to
295         next page.\MessageBreak \fi
296     Reported}%
297     \ifL@nextpage \newpage \fi
298     \fi

```

We (mis)use the length `\L@first` to compute the width of the text eventually coming before the dropped capital. It is reset later on to hold the first line's length.

```

299     \setlength{\L@Pindent}{\LettrineWidth}%
300     \addtolength{\L@Pindent}{-\L@hang\LettrineWidth}%
301     \settowidth{\L@first}{\L@ante}%
302     \addtolength{\L@Pindent}{\L@first}%
303     \addtolength{\L@Pindent}{\L@Findent}%
304     \setlength{\L@first}{\linewidth}%
305     \addtolength{\L@first}{-\L@Pindent}%

```

Now let's compute `\L@Nindent` and `\L@next` for the next lines.

```

306     \addtolength{\L@Nindent}{\L@Pindent}%
307     \setlength{\L@next}{\linewidth}%
308     \addtolength{\L@next}{-\L@Nindent}%

```

This is for quotation, quote, abstract... environments: `\linewidth` is set by these environments, all we have to do is to shift our text left by `\@totalleftmargin`.

```

309     \addtolength{\L@Pindent}{\@totalleftmargin}%
310     \addtolength{\L@Nindent}{\@totalleftmargin}%

```

Now, set up the shape of the new paragraph (designed by `\parshape`). It obviously depends on the text direction, the code previously available in `lettrine-xetex-bidi.def` for right to left scripts is integrated here now.

```

311     \addtocounter{L@lines}{1}%
312     \addtocounter{L@lines}{\value{L@depth}}%
313     \ifL@RTL
314         \def\L@parshape{\c@L@lines \z@ \the\L@first}%
315     \else
316         \def\L@parshape{\c@L@lines \the\L@Pindent \the\L@first}%
317     \fi
318     \@tempcnta=\tw@
319     \@whilenum \@tempcnta<\c@L@lines\do{%
320         \ifL@RTL
321             \edef\L@parshape{\L@parshape \z@ \the\L@next}%
322         \else
323             \edef\L@parshape{\L@parshape \the\L@Nindent \the\L@next}%
324         \fi
325         \addtolength{\L@Nindent}{\L@slope}%
326         \addtolength{\L@next}{-\L@slope}%
327         \advance\@tempcnta\@ne}%
328     \ifL@RTL
329         \edef\L@parshape{\L@parshape \z@ \the\linewidth}%
330     \else

```



```

331 \edef\L@parshape{\L@parshape \@totalleftmargin \the\linewidth}%
332 \fi

```

Set the `\L@lbox` box in horizontal mode for tagging, see <https://github.com/latex3/tagging-project/issues/481>.

```

333 \noindent
334 \parshape=\L@parshape\relax
335 \setupL@lbox

```

Write the dropped capital into the left margin, and wrap the rest of paragraph around it.

```

336 \llap{\smash{\mbox{\L@ante}\raisebox{\L@lraise}{\usebox{\L@lbox}}}}%
337 \ifL@grid\else\rule{\z@}{\L@finalht}\fi
338 \hskip \the\L@Findent}%
339 {\LettrineTextFont{#3}}%

```

A `\parshape` reset is required in abstract, quote and quotation environments beginning with `\lettrine` and spreading over several paragraphs. When the list ends, `\parshape` returns to 0.

```

340 \ifnum\@listdepth>0 \Lreset@listparshape \fi
341 }

```

This ends the definition of `\lettrine`; `\Lreset@listparshape` adds the `parshape` reset to the first occurrence of `\everypar` following the `\lettrine` command.

```

342 \newtoks\Llist@everypar
343 \def\Lreset@listparshape{%
344 \let\Lnew@everypar\everypar
345 \Llist@everypar=\expandafter{\the\everypar}%
346 \Lnew@everypar={\the\Llist@everypar
347 \parshape=\@ne \@totalleftmargin \linewidth \relax
348 \let\everypar\Llist@everypar
349 }%
350 }

```

Compatibility with the `bidi` package (loaded *after* `lettrine`).

```

351 \AtBeginDocument{%
352 \IfPackageLoadedTF{bidi}{\eqnewif{\ifL@RTL}{\if@RTL}}{}%
353 }

```

3 Configuration file

```
354%% lettrine.cfg: configuration file for lettrine.sty
355%%
356%% If you want to customize lettrine, please *do not* hack into the
357%% code, copy this file to your working directory and customize the
358%% copy as you like.
359%%
360%% Uncomment any of these lines and change the parameters' values
361%% to fit your needs (see lettrine.dtx).
362%%
363%%\setcounter{DefaultLines}{2}
364%%\setcounter{DefaultDepth}{0}
365%%
366%% These are *decimal* numbers:
367%%\renewcommand{\DefaultLoversize}{0}
368%%\renewcommand{\DefaultLraise}{0}
369%%\renewcommand{\DefaultLhang}{0}
370%%
371%% These are *lengths* (don't forget the unit):
372%%\setlength{\DefaultFindent}{0pt}
373%%\setlength{\DefaultNindent}{0.5em}
374%%\setlength{\DefaultSlope}{0mm}
375%%\setlength{\DiscardVskip}{1pt}
376%%
377%% Theses are *flags* (value=true/false):
378%%\LettrineImagefalse
379%%\LettrineOnGridfalse
380%%\LettrineRealHeightfalse
381%%\LettrineMoveAtEOPfalse
382%%
383%% This is a *command*, define it as \relax if you dont want the second
384%% mandatory argument of \lettrine[]{}{} to be typset in small caps.
385%%\renewcommand*\LettrineTextFont{\scshape}
386%%
387%% Theses are *commands* (value=string, only height matters):
388%%\renewcommand{\LettrineTestString}{EFTZ}
389%%\renewcommand{\LettrineSecondString}{x}
390%%
391%% In case you want to set parameters for some letters
392%% in file `optfile.cfl'
393%%\renewcommand{\DefaultOptionsFile}{optfile.cfl}
```

4 Change History

Changes are listed in reverse order (latest first) from version 1.5

v2.83	<code>\lettrine</code> : now defined using <code>\NewDocumentCommand</code> 13	(<code>lettrine.ins</code> deleted). 8
	Remove unnecessary usage of <code>\L@tbox</code> (safer for tagging). 17	Package options and <code>\lettrine</code> options no longer depend on <code>xkeyval</code> , they are based on <code>ltkeys.dtx</code> 9
v2.82	<code>\computeL@dimens</code> : Stop using <code>\L@lbox</code> to compute the initial's <code>dimens</code> (solves tagging issues with images). 12	<code>\compute@fontsize</code> : Computation of <code>\L@factor</code> for <code>\fontsize</code> done by the <code>xfp</code> package. 12
v2.81	General: Added <code>\L@actual</code> and <code>keyval</code> option 'actualtext' for image tagging. 8	<code>\lettrine</code> : Options from the per letter config file are now handled by LaTeX command <code>\SetKeys</code> . . . 14
	<code>\lettrine</code> : Reset <code>\L@lbox</code> and <code>\L@tbox</code> after starting the new paragraph as suggested by Ulrike Fischer for tagging. 17	Replace <code>\usebox</code> by <code>\unhcopy</code> for box <code>\L@tbox</code> to allow footnote calls and microtype action. 17
v2.80	General: New <code>keyval</code> option: 'nextpage' (true/false), default is false. 2	v2.30
	<code>\lettrine</code> : Move the paragraph to next page if the dropped cap doesn't fit in the current one. . . . 15	General: Added global options to package <code>lettrine</code> 9
v2.70	General: Read the config file only once, its content is added to token register <code>\Lettrine@tweaks</code> 10	v2.23
v2.61	<code>\lettrine</code> : Include the 'ante' box into the <code>\smash</code> command in case it is shifted down. 17	General: Documentation cleanup. . . 1
v2.60	<code>\lettrine</code> : <code>\L@parshape</code> compatible with <code>xetex</code> bidi RTL typesetting. . 16	v2.22
v2.52	General: New option 'viewport' to be passed to <code>\includegraphics</code> 2	<code>\compute@fontsize</code> : Warn if <code>\fontsize</code> computation fails due to division by 0. 12
v2.50	General: <code>\DiscardVskip</code> default value enlarged from 0.2pt to 1pt. . 8	<code>\lettrine</code> : <code>\@totalleftmargin</code> is the correct indentation for quote, quotation and abstract environments. 16
	<code>\lettrine</code> : Remove the top <code>\vskip</code> , smash the dropped cap, add a <code>\rule</code> to mimic its height above the baseline instead. 17	<code>\parshape</code> reset added in lists. . . 17
v2.40	General: <code>lettrine.dtx</code> auto-generates <code>lettrine.sty</code> and <code>lettrine.cfg</code>	v2.21
		General: Code clean up, new commands <code>\computeL@height</code> , <code>\compute@fontsize</code> , <code>\setupL@lbox</code> 11
		v2.2
		General: Rollback mechanism used for recovering older versions. . . . 8
		v2.1
		General: New option 'refstring'. . . . 8
		Newif <code>\ifLettrineVone</code> and new option 'Vone' (removed in v2.2, rollback preferred). 8
		<code>\compute@fontsize</code> : Computation of <code>\L@factor</code> for <code>\fontsize</code> done by the <code>minifp</code> package. 12
		<code>\computeL@height</code> : Height computations moved out of <code>\LettrineFont</code> : <code>\global</code> settings no longer required. 11

v2.0		Added two keyval options: 'grid' (true/false) and 'novskip' to override <code>\DiscardVskip</code>	2
	<code>\computeL@height</code> : Store targeted dimensions of the dropped capital (ht, dp, tht) for further use.		11
	<code>\lettrine</code> : Add informations about targeted and actual height of the initial to the .log file.		15
	<code>\LettrineTestString</code> : changed from 'ABCDEFGHJKLMNOQ-PRSTUVWXYZ' to 'EFTZ' as some capitals like C, G, O, Q or X might be slightly taller (possible optical correction).		9
v1.9	General: New customisable string <code>\LettrineSecondString</code> to tune the initial's height.		3
	New keyval option: 'realheight' (true/false) and new global flag <code>\ifLettrineRealHeight</code>		2
	<code>\computeL@height</code> : <code>\theL@lines</code> changed to <code>\value{L@lines}</code> . Needed for babel-hebrew which redefines <code>\@arabic</code>		11
	<code>\lettrine</code> : <code>\theDefaultLines</code> changed to <code>\value{DefaultLines}</code> , same with <code>\theDefaultDepth</code> . Needed for babel-hebrew which redefines <code>\@arabic</code> . Thanks to Ulrike Fischer for providing the fix.		13
	<code>\theL@depth</code> changed to <code>\value{L@depth}</code>		16
	Use the second mandatory argument of <code>\lettrine</code> or <code>\LettrineSecondString</code> (which defaults to 'x') to compute <code>\L@height</code> . This is controlled by the 'realheight' flag.		14
v1.8	General: Added newif <code>\ifLettrineOnGrid</code> and new dimen <code>\DiscardVskip</code> , default (0.2pt) set for compatibility with previous releases.		8
		General: New counter to add lines for dropped capitals with positive depth, like Q.	1
		<code>\lettrine</code> : Measure and store the initial's final dimensions.	14
		<code>\lettrine</code> : Remove \$ around <code>\smash</code> and add <code>\relax</code> . Bug pointed out by David Monniaux. Correction by Enrico Gregorio.	17
		<code>\LettrineTestString</code> : (new) it defaults to 'ABCDE-FGHJKLMNOQPRSTUVWXYZ'. In previous versions height computations were based on letter 'X' which might not exist in some (rare) fonts. Pointed out by Raphaël Pinson.	9
		General: Add a flag to switch to images in eps or pdf format. Suggested by Bill Jetzer.	2
		Added newif <code>\ifL@grid</code>	8
		Added newif <code>\ifL@image</code>	8
		Added newif <code>\ifLettrineImage</code>	8
		<code>\lettrine</code> : Add braces around #3 to allow commands taking an argument (such as <code>\MakeLowercase</code>) in <code>\LettrineTextFont</code> . Suggested by Philipp Lehman.	14
		General: <code>\LettrineOptionsFor</code> and <code>\LettrineWidth</code> added.	10